TEXcount* Perl script for counting words in LATEX documents Version 2.2

ABSTRACT

T_EXcount is a Perl script for counting words in LAT_EX documents. It recognizes most of the common macros, and has rules for which parameters to count and not to count; the main text is counted separately from the words in headers and in captions of figures and tables. Finally, it produces a colour coded version of the parsed document, either as a text document or as HTML to be viewed in a browser, indicating which parts of the document have been included in the count.

Contents

1	What does TEXcount do?	1
	1.1 What T_{E} X count does not do	2
2	Syntax and options	2
	2.1 Running T _E Xcount	2
	2.2 Parsing details	4
	2.3 Summary information	4
	2.4 Parsing options	5
	2.5 File inclusion	5
3	What T _E Xcount counts	5
4	Macro handling rules	6
	4.1 Cautions!	7
5	TFX count instructions in the LATFX document	7
	5.1 Ignoring segments of the file	7
	5.2 Adding subcount break points	7
	5.3 Adding macro handling rules	8
6	License	9

1 What does T_EXcount do?

 T_EX count is a Perl script made for counting the words in a LATEX document. Since LATEX documents are formated using lots of macro instructions and often contain both mathematical formulae and floating tables and figures, this is no trivial task.

Simple solutions to counting the words consists of detexing the documents, which often merely consisty of ignoring the T_EX and LT_EX instructions. This is a bad solution since it will usually result in overestimating the number of words as mathematical formulae, citations, labels and references are counted.

A perfect solution, if such exists, needs to take into account how LATEX interprets each macro instruction. The simplest approach to taking this into account consisty of making the count based on the typeset

^{*}Copyright (2008-2009) of Einar Andreas Rødland, distributed under the LATEX Project Public Licence (LPPL).

document, but this too tends to over-estimate the word count as mathematical formulae, table contents and even page numbers may get counted.

A simple but robust approach, which is the one I have taken with T_EX count, is to parse the LAT_EX document using simple rules for how to interpret the different T_EX and LAT_EX instructions. Rules for most of the common macro instructions are included in T_EX count, and it is possible to specify new rules in the T_EX document.

The primary focus of T_EXcount is to:

- provide an accurate count of the number of words in LATEX documents;
- exclude or count separately document elements which are not part of the main text such as figure captions;
- enable the user to, with relative ease, check how T_EXcount has parsed the document and which elements have been counted and which have not.

The last point on this list is one of the most important. Having an accurate word count is of little value unless you know that it is accurate; conversly, trusting an inaccurate word count can be potentially harmful, e.g. if you are submitting a paper or a report which has a strict word limit.

Since T_EXcount relies on a relatively simple rules for how to handle the different macros and only performs limited checks on the validity of the LAT_EX document, it is your responsibility to make sure the document actually typesets in LAT_EX before running it through T_EXcount. Also, T_EXcount relies on handling macros taking parameters enclosed with { and }, and on ignoring options enclosed by [and]: macros with significantly different syntax such as \vskip cannot be handled.

1.1 What TFX count does not do

While an ideal solution should be able to expand the macro instructions, thus being able to handle new macros, that would at it's worst require reimplementing much of T_EX , something that is clearly unrealistic. While some limited methods for handling new macros based on definitions in the file might be done, I have opted for a simpler solution: to define rules stating which paramters to count and which to ignore. Thus, T_EX count cannot handle macros that may take a variable number of parameters. Nor can it handle macros that takes parameters on forms other than {parameter}.

In general, while T_EX count does the parsing in some detail, it does not do it exactly as T_EX does it. In some respects there may therefore be critical difference: e.g. while T_EX reads one character at a time, T_EX count reads one word at a time, so while LAT_EX would interpret \cite me as \cite{m}e, T_EX count would interpret it like \cite{m}.

Another issue is that, since T_EX count does not know how to expand macros, it cannot handle macros like $\mbox{maketitle}$. Instead, it will count $\title{title text}$ when it occurs.

For users of languages containing letters other than A to Z, there may be an additional challenge. The script relies on Perl to recognize words as sequence of letters, and must therefore know which characters are considered to be letters. The Perl locale may be changed (as of now this is hard-coded!) to accommodate this, but this does not work for special letters encoded using TEX or LATEX macros or codes: e.g. \aa and \"a will not be understood to be letters in the present implementation, whereas a and a will. I have added a relaxed mode where some special character and character modifying macros are allowed as parts of words, which may be activated with the option -relaxed.

2 Syntax and options

2.1 Running T_EXcount

The command to run TFX count may vary slightly depending on the operating system and the local settings.

Under Linux/Unix, it should be sufficient to run texcount.pl provided it is in the PATH and has been made executable (chmod u+x texcount.pl). The first line of the file, the one starting with #!, tells Linux/Unix which command to use to run the script. This may either direct to the perl command giving the full path to it (use which perl if you need to find out where perl is located) or, as is done in more recent versions of TEXcount, contain the line #!/usr/bin/env perl which should find the correct location for perl (provided the program /usr/bin/env is available).

Under Windows, running texcount from the command line suffices if texcount.pl is in the path and pl-files are defined to run as Perl scripts.

Alternatively, if the above methods do not work, you may have to execute it more exclicitly under Perl using perl texcount.pl. You then need to have the perl executable file in the path or give the explicit path.

I will simply write ${\tt texcount}$ in this manual for the code to execute the script. Then, the syntax becomes

texcount [options] [files]

where the options may be amongst the following:

- **-v** Verbose (same as -v3).
- -v0 No details (default).
- -v1 Prints counted text, marks formulae.
- -v2 Also prints ignored text.
- -v3 Also includes comments and options.
- -v4 Same as -v3 -showstate.
- -showstate Show internal states (with verbose).
- -brief Only prints a one line summary of the counts.
- -q, -quiet Quiet mode, does not print error messages. Use is discouraged, but it may be useful when piping the output into another application.
- -total Only give total sum, no per file sums.
- -1 Same as specifying -brief and -total, and ensures there will only be one line of output. If used with -sum, the output will only be the total number.
- -sub[=...], -subcount[=...] Generate subcounts. Valid option values are none, part, chapter, section and subsection (default), indicating at which level subcounts are generated.
- -sum[=n, n, ...] Produces total sum, default being all words and formulae, but customizable to any weighted sum of the seven counts (list of weights for text words, header words, caption words, headers, floats, inlined formulae, displayed formulae).
- -nc, -nocol No colours (colours require ANSI).
- -relaxed Relaxes the rules for matching words and macro options.
- -inc Include tex files included in the document.
- -noinc Do not include included tex files (default).
- -dir[=...] Working directory, either taken from the first file given, or specified.
- -utf8, -unicode Turn on Unicode (UTF-8) support.

- -ch, -chinese, -zhongwen Turn on Chinese mode in which Chinese characters are counted. Switches on UTF-8 mode.
- -jp, -japanese Turn on Japanese mode in which Japanese characters (kanji and kana) are counted. Switches on UTF-8 mode.

-html Output in HTML format.

-htmlcore Only HTML body contents.

-codes Display an overview of the colour codes. Can be used as a separate option to only display the colour codes, or together with files to parse.

-nocodes Do not display overview of colour codes.

-h, -?, -help, /? Help.

-version Print version number.

-license License information.

If more than one file is given, T_EXcount will perform the count on each of them printing the results for each, then print the total sum at the end.

2.2 Parsing details

By selecting one of the -v options, you can choose how much detail is printed. This is useful for checking what T_EXcount counts. The option -showstate shows the internal state and is for debugging purposes only.

The output is colour coded with counted text coloured blue, other colours for other contexts. The colour coding is made using ANSI colour codes. These should work when printed directly to Linux xterm window, but need not work if piped through more or less: with less you need to use the option -r for the colours to be shown correctly.

Under Windows or other operating systems, the ANSI colour codes cannot be expected to work, in which case the option -nocol (-nc) may be used to turn off colour coding; instead I recommend using HTML output which can be viewed in a browser.

To print the details encoded as HTML code, use the option <code>-html;</code> alternatively, with <code>-htmlcore</code> only the HTML body is printed. On Windows, I suggest using the options <code>-html -v</code> to get full detail, save this to a HTML file, e.g. using

```
texcount -html -v texfile.tex > details.html
```

and then view the details.html file in a browser.

2.3 Summary information

By default, T_EXcount outputs counts of text words, header words, caption words, number of headers, number of floats/figures, number of inlined formulae, and number of displayed formulae, and lists each of these counts. To shorten this to a one-line format, specify -brief.

To get T_EXcount to produce a total count, specify -sum: this will compute the sum of all words plus the number of formulae. A customized sum may be computed by speficying $-sum=n, n, \ldots$ with up to seven numbers separated by commas giving the weight (0=don't count, 1=count once) of each of the seven counts: e.g. the default is equivalent to -sum=1,1,1,0,0,1,1. To count words only, use -sum=1,1,1. Higher weights may also be used, e.g. to count displayed formulae or floats/figures as a given number of words.

Specifying -sum has two main effects: the cumulative sum is added to the output in verbose formats, and the sum is added to the summary. If combined with -brief, the option -total is automatically set, resulting in a one line output containing only the total sum.

For adding subcounts e.g. by sections, the option -sub(or -subcount) may be used. By default, this produces subcounts by part, chapter, section and subsection which are listed in a brief format. One may, however, specify -sub= followed by part, chapter, section, or subsection (default when given without value). Break points which initiate a new subcount may also be specified within the LATEX document using TC:break name.

If included files are included in the count (-inc), counts per file will be produced followed by a total count. To suppress per file counts, the option -total may be used.

2.4 Parsing options

 T_EX count uses regular expressions to identify words and macro options. By default, these are moderately strict, but can be relaxed using the option -relaxed. This allows more general document elements to be identified as words or macro options, which may sometimes be desired, but may also have undesirable effects, so check the verbose output to verify that T_EX count has counted the appropriate elements.

Macro options, i.e. [...] after macros and macro parameters are ignored. Since T_EX count has no specific knowledge of which macros take options, this is a general rule. In order to avoid that uses of [...] that are not macro options are mistaken as such, T_EX count makes some restrictions on what may be contained in such an option. By default, this restriction is relatively strict under the assumption that it is better to count a few macro options as words than risk large fragments of text to be ignored. However, if your document contains macro options with more complicated values (e.g. certain special characters or macros), using -relaxed may help handle these correctly.

By default, T_EX count does not allow special characters or macros to be part of words. This may cause problems if character modifiers or some special characters are used which are entered as macros. The -relaxed option makes the word recognition regular expression somewhat more general.

2.5 File inclusion

If the option -inc is used, T_EXcount will automatically count documents that are included (using \input or \include. As when giving a list of files to count, it will print the sum per file and a total sum at the end. The default is -noinc indicating that included documents are not counted.

By default, TEXcount assumes paths are relative to the working directory. Alternatively, an explicit path may be given using -dir=path. Note that the path must end in the path delimiter symbol (depending on the operating system, / under Linux, \under Windows). If only -dir is used, the path of the first file given will be used.

Note that included documents are analysed as separate files: the text of included documents are thus not included where the <code>\input</code> or <code>\include</code> is located. This has two consequences. First, since word counts are produced per file, subcounts f.ex. by chapter will only include the text in the same file as the <code>\chapter</code> macro. Secondly, if TC-instructions to TEXcount are embedded in the LATEX document, e.g. defining additional macro handling rules, these take effect in the order they are parsed by TEXcount. Since included documents are parsed after the parent document, definitions in the parent document will be in effect for the included documents; definitions made in the included documents.

3 What T_EXcount counts

The primary role is to count the words. It is not entirely clear what should be considered words, so I have had to make some decisions. A sequence of letters is certainly a word. I also count acronyms like 'e.g.', dashed words like 'over-all', and 'it's' as one word. I have decided also to count numbers as words unless they are placed in a math environment.

Mathematical formulae are not counted as words. Instead, TEXcount counts the number of inline formulae (\$maths\$) and displayed formulae separately.

Text in headers (\title, \section, etc.) are counted separately: it counts the number of headers as well as the number of words in headers.

Floating environments (or potentially floating environments) such as tables and figures are not counted as text, even if the cells of a table may containt text. However, if they have captions, these will be counted separately much like headers were. By default, begin–end environments do not modify the parsing state: i.e. environments within the text are counted as text, etc. Rules for the most common environments, at least those that require non-default treatment, should be predefined, but you may have to add more rules if you use environments defined in packages or by yourself.

Some macros are words by themselves: e.g. \LaTeX . These are counted as words, but you cannot expect TEXcount to count something like $\LaTeX-word$ or $\{\TeX\}\$ ount as one word, although the above explanation inicates that it should: TEXcount will in both cases evaluate the macro and the following text separately and thus count them as separate entities.

4 Macro handling rules

A very few rules are hard-coded, e.g. that text between $\common \common \com$

- **macro** In its simplest form, this type of rule just tells how many parameters to ignore following the macro. More generally, one may specify the number of parameters a macro takes and how each of these should be handled. Options enclosed in [] before, between and after parameters are also ignored; this also applies to macros not specified here, so for a macro with no rule, immediately following []-options will be ignored. (This type of rule was called an exclude rule in older versions of TEXcount, the reason being that the rule originally only gave the number of parameters to ignore following a given macro.)
- **header** Some macros are specified to be counted as headers. This initially only indicates that the macro should cause the number of headers to be increased by one, but an additional rule is added to the macro-rule to count the following parameter as header text.
- group For groups enclosed by \begin{name} and \end{name}, there are rules specifying how the contents should be interpreted. A macro rule is added for beginname (without the backslash!) which is TEXcount's internal representation of \begin{name}. Some special characters will be ignored if following name, e.g. \begin{equation*} will be treated as \begin{equation} since * is ignored.
- **macroword** This type of rule indicates that the macro itself represents one or more words. Initially, \LaTeX and \TeX are defined with values 1 indicating that each represents one word.
- **preamble** A few macros should be counted even if they are in the preamble. In particular, \title{title text} is counted as a header assuming it will later be used to produce a title.
- float inclusion Within floats (begin-end groups defined with parsing status -1) there may be texts that should still be counted: in particular captions. These are specified with the float inclusion rule.
- file include If -inc is specified, included files will also be parsed and the total presented at the end. Initially, \input and \include trigger file inclusion, but more file inclusion macros may be added.

A macro parameter is normally something on the form {something}; more generally it may be anything T_EXcount parses as a single unit (or token), e.g. a macro, but since T_EXcount parses word by word rather than character by character this may not always be correct if parameters are not {}-enclosed or macros.

4.1 Cautions!

Since the rules are of a relatively general nature, macros that have a great deal of flexibility are hard to deal with. In particular this applies to macros with a variable number of parameters or where the handling of the parameters are not constant.

Also, []-options following macros and macro parameters are always ignored, and T_EX count gives no flexibility in over-ruling that. Since options are, by definition of the term, meant to be optional, extending T_EX count to handle them would require extensive reprogramming as well as require much more detailed macro definition rules than what is now possible.

More critically, since T_EX count does not really know which macros take options or not, just assumes that options should never be included, there is some risk of misinterpreting as an option something that is not: e.g. \bf[text]. This is not likely to be a frequent problem. However, if something like \bf[a lot of text] gets ignored because it is considered an option, it can influence the word count substantially. I have therefore been somewhat restrictive with what (and how much) can go into an option.

More advanced macros are not supported and can potentially confuse T_EXcount. In partcular, if you define macros that contain unbalanced begin–end groups, this will cause problems as T_EXcount needs to keep track of these to know where different groups start and end.

5 T_EXcount instructions in the LAT_EX document

It is possible to give some instructions to T_EX count from within the L^AT_EX document. The general format of these instructions are

```
%TC:instruction [name] parameters
```

where the name parameter is used with macro handling instructions to specify the macro or group name for which the rule applies.

Note that the comment should be on a separate line, and that instructions are case sensitive.

5.1 Ignoring segments of the file

The TC-instruction ignore, later canceled by endignore, may be used to turn of all counting in a segment of the LATEX file. The ignored segment should thus be started by

%TC:ignore

end ended by

```
%TC:endignore
```

causing all text inbetween to be ignored. Note that TEXcount still parses this text and may be affected by unbalanced brackets.

5.2 Adding subcount break points

By specifying -sub, T_EXcount can produce subcounts, e.g. per section. Alternatively, or in addition, explicit break points can be entered in the LAT_EX document using the TC-instruction break. These take the form:

```
%TC:break title
```

A title (or name) may be given to identify the break point.

If you define new section macros or macros you wish to cause a break point, these may be specified using the TC-instruction breakmacro:

```
%TC:breakmacro macro label
```

This defines the given macro to cause a break point, and uses the given label to indicate the type of break (e.g. Section, Chapter, etc.).

5.3 Adding macro handling rules

Adding your own macro handling rules is relatively simple. Although editing the script is possible, and not too difficult, this has the disadvantage that the modifications will be lost if updating to a new version of T_EX count. A better and more flexible solution is to include instructions to T_EX count in the LAT_EX documents, alternatively to make a definition file in which new macro handling rules are defined.

Comment lines on the form

%TC:instruction name parameters

encountered in the parsed document are used to add macro handling rules. The instruction states what kind of rule, the name specifies the macro or begin-end group, and parameters specify the rule. Be aware that these are not syntax checked and may produce either Perl errors or incorrect results if entered incorrectly.

Macro names should be entered with their full name starting with backslash. Internally, begin-end groups are represented using macro names beginname without backslash, but rules for begin-end groups are specified through a separate TC-instruction.

Note that macro handling rules are added successively throughout the session: i.e. if more files are parsed, handling rules from previously parsed files still apply. This has advantages as well as disadvantages. If you give a list of files with the rules specified in the first file, these rules will be applied to all the documents. However, if you use the -inc option, included files will be parsed only after TEXcount has finished parsing the file in which they are included, so any rules specified in these will not apply to the initial document.

The instructions may be one of the following:

- **macro** Define macro handling rule for the given macro. Takes one parameter which is either an integer or a []-enclosed array of integers (e.g. [0,1,0]). An integer value n indicates that the n first parameters to the macro should be ignored. An array of length n indicates that the first n parameters should be handled, and the numbers of the array specifies the parsing status (see below) with which they should be parsed. Giving the number n as parameter is equivalent to giving an array of n zeroes ([0, ..., 0]) as zero is the parsing status for ignoring text.
- **macroword** This defines the given macro to represent a certain number of words, where the number is given as the parameter.
- **header** Define macro to give a header. This is specified much as the macro rule. The added effect is that the header counter is increase by 1. Note, however, that you should specify a parameter array, otherwise none of the parameters will be parsed as header text. The parser status for header text is 2, so a standard header macro that uses the first parameter as header should be given the parameter [2].
- **breakmacro** Specify that the given macro should cause a break point. Defining it as a header macro does not do this, nor is it required of a break point macro that it be a header (although I suppose in most cases of interest it will be).
- **group** This specifies a begin-end group with the given name (no backslash). It takes two further parameters. The first parameter specifies the macro rule following \begin{name}. The second parameter specifies the parser status with which the contents should be parsed: e.g. 1 for text (default rule), 0 to ignore, -1 to specify a float (table, group, etc.) for which text should not be counted but captions should, 6 and 7 for inline or displated math.
- **floatinclude** This may be used to specify macros which should be counted when within float groups. The handling rules are spefified as for macro, but like with header an array parameter should be provided and parameters that should be counted as text in floats should be specified by parsing status 3. Thus, a macro that takes one parameter which should be counted as float/caption text should take the parameter [3].

- preambleinclude The preamble, i.e. text between \documentclass and \begin{document}, if
 the document contains one, should generally not be included in the word count. However, there
 may be definitions, e.g. \title{title text}, that should still be counted. In order to be able
 to include these special cases, there is a preambleinclude rule in which one may speficy handling
 rules for macros within the preamble. Again, the rule is speficied like the macro rules, but since the
 default is to ignore text the only relevant rules to be specified require an array.
- **fileinclude** By default, T_EXcount does not automatically add files included in the document using \input or \include, but inclusion may be turned on by using the option -inc. If other macros are used to include files, these may be specified by adding fileinclude rules for these macros. The specification takes one parameter: 0 if the file name should be used as provided, 1 if file type .tex should be added to files without a file type, and 2 if the file tyle .tex should always be added.

The parser status is used to dictat how each parameter should be parsed. E.g. if a macro has its parameter set defined by [1, 0, 1], it means the first and third parameters are counted as text words (parser status 1) whereas the second is ignored (parser status 0). Another case is \renewcommand which is defined as [-3, -2]: the first parameter is to be read without interpreting the contents (which is going to be a macro name whose macro handling rules should not be applied here), and the second parameter should be ignored without requiring that begin–end groups be balanced. The different parsing states are:

- 0: ignore text, i.e. do not count, but will still parse the code;
- 1: count as text (i.e. count words);
- 2: count as header text;
- 3: count as float/caption text;
- −1: float, ignore text but look for floatinclude macros;
- -2: stronger ignore which ignore begin-end groups, e.g. to use in macro definitions where begin-end groups need not be balanced;
- -3: even stronger ignore, handles macros as isolated tokens without handling their parameters, to use with macro definitions like \newcommand and \def;
- -9: preamble, ignore text but look for preambleinclude macros.

Here are some examples together with corresponding macro definitions:

```
%TC:macroword \TeXcount 1
\newcommand\TeXcount{{\TeX}count}
%TC:macro \NB 1
\newcommand\NB[1]{\marginpar{#1}}
%TC:header \newsection [2,0]
\newcommand\newsection[2]{\section{#1}\label{sec:#2}}
%TC:group theorem 0 1
\newtheorem{theorem} Theorem}
```

The predefined rules can easily be read off the script file: they are hash maps defined at the beginning of the script with names TeXmacro, TeXheader, etc.

6 License

The T_EXcount package—script and accompanying documents—is distributed under the LAT_EX Project Public License (LPPL) http://www.latex-project.org/lppl.txt

which grants you, the user, the right to use, modify and distribute the script. However, if the script is modified, you must change its name or use other technical means to avoid confusion with the original script.