

Contents

1 Module Inifiles : This library reads ini format property files	1
--	---

1 Module Inifiles : This library reads ini format property files

`exception Invalid_section of string`

raised if you ask for a section which doesn't exist

`exception Invalid_element of string`

raised if you ask for an element (attribute) which doesn't exist, or the element fails to match the validation regex

`exception Missing_section of string`

raised if a required section is not specified in the config file

`exception Missing_element of string`

raised if a required element is not specified in the config file

`exception Ini_parse_error of (int * string)`

raised if there is a parse error in the ini file it will contain the line number and the name of the file in which the error happened

```
type attribute_specification = {
  atr_name : string ;
  atr_required : bool ;
  atr_default : string list option ;
  atr_validator : Pcre.regexp option ;
}
```

The type of an attribute/element specification

```
type section_specification = {
  sec_name : string ;
  sec_required : bool ;
  sec_attributes : attribute_specification list ;
}
```

The type of a section specification

```
type specification = section_specification list
```

The type of a specification

```
class inifile : ?spec:specification -> string ->
  object
```

```

method getval : string -> string -> string
    get a value from the config object raise Invalid_section, or invalid_element on error.
    getval section element

method getaval : string -> string -> string list
    get a value from the config object. return a list of all the objects bindings. If the key is
    listed on more than one line it will get n bindings, where n is the number of lines it is
    mentioned on. raise Invalid_section, or invalid_element on error. getaval section
    element

method setval : string -> string -> string -> unit
    set a value in the config create a new section, and/or element if necessary. setval section
    element

method delval : string -> string -> unit
    delete the topmost binding (the one returned by getval) from the section sec. Possibly
    exposing another binding. raise Invalid_section on error. delval sec elt

method save : ?file:string -> unit -> unit
    save the changes you have made optionally save to a different file

method iter : (string -> string -> unit) -> string -> unit
    iterates across a section. passes all key value pairs to f exactly once.

method sects : string list
    returns a list of all sections in the file

method attrs : string -> string list
    return all the attributes of a section

end

send the name of an ini file to the constructor the file must exist, but can be empty

val fold : ('a -> configparser -> 'a) -> string -> 'a -> 'a
    Executes a fold left across a directory of ini files (skips files which do not end with .ini). fold
    f path a computes (f ... (f (f file1 a) file2) fileN)

```